



1. Content

1. Content.....	1
2. Change history.....	2
3. Overview.....	2
4. Introduction.....	2
5. Getting started.....	3
6. Submitting SOAP to the gateway.....	4
7. Basic commands.....	4
7.1 Authentication and session ids.....	4
7.2 Ping.....	5
7.3 Send a message.....	5
7.4 Query a message.....	6
8. Message parameters.....	8
8.1 Table of parameters.....	8
8.2 Message parameters in detail.....	10
9. Additional Commands.....	18
9.1 Delete/Stop message.....	18
9.2 Query balance.....	18
9.3 Coverage query.....	19
9.4 MMS Push.....	19
9.5 WAP push service indication.....	20
9.6 Get message charge query.....	21
9.7 Token (voucher) pay.....	22
10. Batch messaging.....	22
10.1 Start batch.....	23
10.2 Sending messages to existing batch.....	23
10.3 Quick send to batch.....	24
10.4 End batch.....	24
11. Message examples.....	25
11.1 Simple examples.....	25
11.2 Batch SMS examples.....	27
12. Appendix A: Error codes.....	30
13. Appendix B: Message statuses.....	31
14. Terminology.....	32
15. Contact details.....	33

2. Change history

Approximately six (6) months of changes are reflected.

Visit http://www.clickatell.com/downloads/soap/Clickatell_SOAP.pdf to check for updates to this document

Version	Date	Section	Changes to Documentation
1.1.4	4 February 2009	6	Added Visual Studio workaround information
1.1.3	15 January 2009	All	Added update link; moved terminology table.

3. Overview

This document is intended for those users who wish to develop applications that make use of our SMS gateway.

It is recommended that you have an understanding of profiles before reading this document. Information is available at <http://support.clickatell.com/guides/clickatell/routing.php>. Please note that we request delivery acknowledgement for **every** message we send although delivery acknowledgement status will only be delivered to you if requested.

There are a number of different ways of gaining access to the gateway:

- SMTP - enabling a server or client generated email to be delivered as an SMS.
- HTTP / HTTPS - submitting either a POST or GET to the API server.
- FTP – uploading a text file to our FTP Server.
- XML – posting to our gateway using XML over HTTP/S.
- COM Object – for Windows based development.
- SOAP – Submit SOAP packets over HTTP/S
- SMPP – customers requiring a high throughput binary socket connection.

In order to reduce testing costs, Clickatell offers a test number range. Messages sent to any number on this prefix will only be charged 1/3 of a credit. Use the number 279991xxxxx (for South Africa) or 1999xxxxxxx (for the U.S.) where “xxxxx” represents any numeric string. Message statuses will be returned.

We will cover the **SOAP** method in this document. Additional documentation is available for the other methods. Sample code is provided on the site.

4. Introduction

The SOAP API uses **Web Services Description Language**, which is an XML-based language that provides a model for describing Web services.

WSDL is often used in combination with SOAP and XML Schema to provide web services over the Internet. A client program connecting to a web service can read the WSDL to determine what functions

are available on the server. Any special data types used are embedded in the WSDL file in the form of XML Schema. The client can then use SOAP to actually call one of the functions listed in the WSDL.

Note: It is important that the ENTIRE document is read before contacting support. Parameters are case-sensitive. You must use character references for Greek and other extended characters.

5. Getting started

In order to use the Clickatell gateway you need a Clickatell account and at least one registered connection (API sub-product instance) between your application and our gateway. Each connection method is known as a sub-product (of our API product). Here's how:

Step 1 - register for a Clickatell account

If you do not already have a Clickatell account, you need to register for one as per below. Otherwise proceed to Step 2.

- Go to http://www.clickatell.com/products/sms_gateway.php, and choose the appropriate API sub-product (connection method) you wish to use.
- Click on the registration hyperlink.
- Fill out the registration form.

After successfully submitting the form you will automatically be logged into your new account and taken to a page where you can add your chosen API connection.

Step 2 - add a registered API connection (sub-product)

If you are not already logged into your account, then you must do so at <http://www.clickatell.com/login.php>

- Select **Manage my Products** from the top menu.
- Select the API connection type you wish to use from the drop down menu (**Add Connection**).
- Complete the form.

If you register more than one API connection, the description name you enter for each must be unique - you cannot have multiple APIs with the same name.

After successfully submitting the form, your authentication details will be displayed, including each connection's unique API ID (api_id). These authentication details are required when connecting to the Clickatell gateway to send a message.

Note: For more information on managing your API connections within your Clickatell account see our API guide at: http://support.clickatell.com/guides/clickatell/api_guide.php.

6. Submitting SOAP to the gateway

The WSDL for the service is available at the following URL:

<http://api.clickatell.com/soap/webservice.php?WSDL>

Submit your SOAP requests via HTTP or HTTPS to the following URL:

<http://api.clickatell.com/soap/webservice.php>

If you are using .Net, make sure your connection URL doesn't have the ?wsdl at the end of the URL. That is only needed when getting the schema. After you retrieve the schema check your reference.cs file. The URL should be <http://domain.com/soap.php> not <http://domain.com/soap.php?wsdl>

Certain versions of Visual Studio may encounter problems using our SOAP API as our webservice uses a parameter which conflicts with a built-in Visual Studio parameter (this is the **callback** parameter).

As a work-around, we have added a separate webservice - the callback parameter will be called msg_callback in this work-around version.

Location: http://api.clickatell.com/soap/webservice_vs.php (*instead of just webservice.php*)

Callback parameter renamed to msg_callback.

7. Basic commands

The following sections describe each of the operations used in the SOAP specification in more detail.

.

7.1 Authentication and session ids

In order to deliver a message, the system needs to authenticate the request as coming from a valid source. We use a number of parameters to achieve this:

- **api_id:** This is issued to you when you register for the API product. A single Clickatell account may have multiple api_ids associated with it.
- **user:** This is the username of your account.
- **password:** The current password you have set on your account.

Additionally we can enforce an IP lockdown, allowing only requests sent from IP addresses that you have specified under the API product preferences. Please ensure that after testing, you remove all unnecessary IP addresses in your preferences, to tighten up on security.

You can have multiple sessions open. However, the session ID will expire after fifteen minutes of inactivity. You will then have to re-authenticate to receive a new session ID. Alternatively you can ping every 10 minutes or so, to ensure that the current session ID is kept live.

This session ID must be used with all future commands to the API, unless you authenticate each time within the command itself.

Name:	auth	
Parameters:	api_id	Required
	user	Required
	password	Required

Name:	Auth Response	
Response Values:	OK: Session ID or ERR: Error number	

7.2 Ping

This command prevents the session ID from expiring in periods of inactivity. The session ID is set to expire after 15 minutes of inactivity. You may have multiple concurrent sessions using the same session ID.

Name:	ping	
Parameters:	session_id	Required

Name:	Ping Response	
Response Values:	Response: OK: or ERR: Error number	

7.3 Send a message

To facilitate sending an SMS with a single command, we have included the ability to post **api_id**, **user** and **password** parameters in *sendmsg*. Using a session ID is preferred to authenticating each time.

Name:	sendMsg	
Parameters:	session_id	Required
	to	Required
	text	Required
	callback	[Optional]

	cliMsgId	[Optional]
	concat	[Optional]
	deliv_ack	[Optional]
	deliv_time	[Optional]
	from	[Optional]
	msg_type	[Optional]
	udh	[Optional]
	unicode	[Optional]
	validity	[Optional]
	req_feat	[Optional]
	max_credits	[Optional]
	queue	[Optional]
	escalate	[Optional]

Name:	sendMsg Response
Response Values:	Response Single Message: ERR: Error number Response Multiple Messages: ERR: Error number To: xxxxxx ERR: Error number To: xxxxxx

7.4 Query a message

This query returns the status of a message. You can query the status with either the **apimsgid** or **climsgid**. The API message ID (**apimsgid**) is the message ID returned by the gateway when a message has been successfully submitted. If you specified your own unique client message ID (**climsgid**) on submission, you may query the message status using this value. You may also authenticate with **api_id**, **user** and **password**.

See appendix B for status codes.

Name:	queryMsg								
Parameters:	<table border="0"> <tr> <td>session_id</td> <td>Required</td> </tr> <tr> <td>apiMsgId</td> <td>Required</td> </tr> <tr> <td>or</td> <td></td> </tr> <tr> <td>cliMsgId</td> <td></td> </tr> </table>	session_id	Required	apiMsgId	Required	or		cliMsgId	
session_id	Required								
apiMsgId	Required								
or									
cliMsgId									

Name:	queryMsg Response
Response Values:	ID: xxxx Status: xxxx or ERR: Error number

Note: Clickatell can also post message status updates to your application via means of a *Callback URL*. This is the recommended method to obtain message status updates as your application is not required to continually poll the Clickatell gateway. Detailed information can be found in the “Callback URL” section under “Message Parameters”.



SOAP API Specification v.1.1.4

Message statuses reports can be viewed online within your Central account. These reports can also be exported in CSV or Excel format.

8. Message parameters

8.1 Table of parameters

There are a variety of messaging and SMS features supported by the gateway, which can be activated by including a number of additional parameters. These parameters include those in the table below. Parameters are case-sensitive.

Name	Parameter name	Short description	Default value	Restricted values
API product ID	api_id	The value for this mandatory parameter can be found or created by logging in online and going to Manage My Products.		
Username	user	The username you specified.		
Password	password	Your account password.		
Session ID	session_id	The session ID from the <i>auth</i> command. Not applicable to the FTP, SMPP or SMTP APIs.		
Destination address	to	The number of the handset to which the message must be delivered. The number should be in international number format.		No '00' prefix or leading "+" symbol should be used.
Text	text	The text content of the message. Note that some characters take up two characters because of GSM encoding standards		http://support.clickatell.com/faq.php?mode=view_entry&kbid=121&kbcat=26
Source address	from	The source/sender address that the message will appear to come from also known as "Sender ID". These must be registered within your online account and approved by us before they may be used. MO numbers rented from us do not require approval.	gateway assigned number	A valid international format number between 1 and 16 characters long, or an 11 character alphanumeric string.
Enable callback	callback	Enables you to receive message delivery statuses via an HTTP, SOAP or XML callback which is posted to a URL of yours using the GET or POST method. This is done every time a message status is updated.	0	0,1,2,3 Read detailed description of parameter.
Delivery time	deliv_time	Delays delivery of SMS to mobile device in minutes relative to the		The upper limit is 7 days, or 10080

Name	Parameter name	Short description	Default value	Restricted values
		time at which the SMS was received by our gateway. This should be greater than 10 minutes for best effect. Smaller time frames may be delivered too soon.		minutes.
Concatenation	concat	Enables you to send messages longer than a standard message.	1	1,2,3
Maximum credits	max_credits	Overrides the maximum charge specified online in "profiles". It works within the bounds of the profiles. In other words a profile must exist for the maximum credit that you set.	As per profiles	0.8,1,1.5,2,2.5,3
Required features	req_feat	Some parameters and features are not set as "required" by default, and may be dropped if the least-cost route does not support them. This parameter allows you to ensure that the features set when an SMS is sent are supported by the gateway used. This could increase the cost per message if a more expensive gateway is used.		Read detailed description of parameter.
Delivery queue	queue	Delivers the message through one of three queues assigned to each client account. Messages in the highest priority queue will be delivered first.	3	1, 2,3 1 is highest priority.
Gateway escalation	escalate	Prompts an escalation to an alternative delivery gateway, should the message be delayed for a set length of time.	0	0 - off 1 - Escalate immediately to an alternative route if messages are queued on the least-cost route.
Mobile originated	mo	We route via a pre-defined carrier to enable the ability for a reply to be received back. This is only applicable to clients that have subscribed to a two-way messaging service.	0	0 – Off. We use our normal routing rules. 1 – Enable Reply.
Client message ID	cliMsgId	Client message ID defined by user for message tracking.		Up to 32 alphanumeric characters. No spaces.

Name	Parameter name	Short description	Default value	Restricted values
Unicode message	unicode	Two digit language code. Convert your text to Unicode [UCS-2 encoding]. See http://www.Unicode.org/ .	0	0 – No Unicode 1 – Send as Unicode.
Message type	msg_type	Optional parameter which must be set to send specially formatted messages; e.g. logos and ringtones.	SMS_TE XT	
User data header	udh	Allows you to set your own message types. Do not use if you set the message type parameter. When set, Clickatell assumes the data is 8 bit. See 8 bit messaging for more information.		Set UDH data manually.
Data	data	The data content of a message, if the UDH component is set manually.		
Validity period	See <i>detailed information on message parameter</i>	The validity period in minutes relative to the time at which the SMS was received by our gateway. The message will not be delivered if it is still queued on our gateway after this time period.	1440 minutes (24 hours)	Set value in X minutes from 1 – 1440 minutes.

8.2 Message parameters in detail

8.2.1 Destination address <to>

SMS messages need to be sent in the standard international format, with country code followed by number. No leading zero to the number and no special characters such as "+" or spaces must be used. For example, a number in the UK being 07901231234 should be changed to 447901231234.

If have you set the preferred dial prefix preference within your client account after logging in on-line, any mobile numbers starting with zero will have the zero stripped and replaced with your default prefix. If the mobile number does not have a zero, the default prefix will not be changed.

8.2.2 Source address <from>

The source address (**from**), also known as the sender ID, can be either a valid international format number between 1 and 16 characters long, or an 11 character alphanumeric string. These must be registered within your online account and approved by us before they may be used. MO numbers rented from us do not require approval

Note that characters such as spaces, punctuation, Unicode and other special characters may not always be supported to all destinations and could interfere with your delivery. We suggest that you refrain from

using such characters on the source address. If this is set, then delivery acknowledgements may be unavailable. The use of an alphanumeric source address with 8-bit messaging may cause message failure. This service is not guaranteed across all mobile networks and may interfere with delivery to certain handsets.

Note: To ensure that this feature is supported when delivering your message, the required features (**req_feat**) parameter for this feature must be set.

8.2.3 Delivery acknowledgment <deliv_ack>

In order to determine whether an SMS has been received by a handset or not, we request delivery acknowledgement for every message we send. The ability to receive reliable delivery acknowledgements varies between mobile networks. Please test to a specific mobile network first, before assuming that you will receive handset acknowledgments for messages that are delivered.

If a GSM handset is 'absent', e.g. switched off or out of coverage, the SMS will be delivered according to a retry cycle once the handset is back in coverage. A delivery receipt will only be returned if and when the retry is delivered. If the validity period or retry cycle (typically 24 hours) is exceeded, the SMS will fail and show 'Error Delivering Message' or status 8.

A delivery acknowledgment can be monitored via the callback URL or online reports.

8.2.4 Callback URL <callback>

Final or intermediary statuses are passed back by the API depending on the **callback** value set in the original post. This is done by means of:

- HTTP GET
- HTTP POST
- XML GET
- XML POST
- SOAP GET
- SOAP POST

The callback URL and optional "Username" and "Password" authentication parameters can be set in the preferences section of the particular API product within your client account, after logging in online. The URL must begin with either *http://* (non-encrypted) or *https://* (encrypted). These are NOT your Clickatell username and password but are a username and password of your choice to add additional security.

The variables returned are **apiMsgId**, **cliMsgId**, **to**, **timestamp**, **from**, **status** and **charge**.

Callback value	Message status types returned	Message status code returned
0	No message status returned.	
1	Returns only intermediate statuses.	002, 003, 011
2	Returns only final statuses of a message.	004, 005, 006, 007, 008, 010, 012
3	Returns both intermediate and final statuses of a	All except 001

message.

Examples

- HTTP

Sample callback to your callback URL using an HTTP get:

https://www.yoururl.com/script.asp?api_id=12345&apiMsgId=996f364775e24b8432f45d77da8eca47&cliMsgId=abc123×tamp=1218007814&to=279995631564&from=27833001171&status=003&charge=0.300000

- XML

The following data is sent in XML MT callbacks in a parameter called 'data':

```
<?xml version="1.0"?>
<callback>
  <apiMsgId>996411ad91fa211e7d17bc873aa4a41d</apiMsgId>
  <cliMsgId></cliMsgId>
  <timestamp>1218008129</timestamp>
  <to>279995631564</to>
  <from>27833001171</from>
  <charge>0.300000</charge>
  <status>004</status>
</callback>
```

Sample callback to your callback URL using an **XML GET**:

[https://www.yoururl.com/script.php?data=<?xml version="1.0"?><callback><apiMsgId>996411ad91fa211e7d17bc873aa4a41d</apiMsgId><cliMsgId></cliMsgId><timestamp>1218008129</timestamp><to>279995631564</to><from>27833001171</from><charge>0.300000</charge><status>004</status></callback>](https://www.yoururl.com/script.php?data=<?xml version=)

- **SOAP**

With the SOAP callback method, a SOAP packet will be sent with a parameter called 'data'. Below is an example packet that will be sent to you via GET or POST.

Example of a SOAP packet that will be sent to you via **GET** or **POST**:

```
<?xml version="1.0" encoding="ISO-8859-1"?>
<SOAP-ENV:Envelope SOAP-ENV:encodingStyle="http://schemas.xmlsoap.org/soap/encoding/"
  xmlns:SOAP-ENV="http://schemas.xmlsoap.org/soap/envelope/"
  xmlns:xsd="http://www.w3.org/2001/XMLSchema" xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
  xmlns:SOAP-ENC="http://schemas.xmlsoap.org/soap/encoding/" xmlns:tns="mt_callback">
  <SOAP-ENV:Body>
    <tns:mt_callback xmlns:tns="mt_callback">
```

```
<api_id xsi:type="xsd:int">1234</api_id>
<apimsgid xsi:type="xsd:string">2e838df2ee3ea418272ae05aaf84ce5d</apimsgid>
<climsgid xsi:type="xsd:string">abc123</climsgid>
<to xsi:type="xsd:string">27999123456</to>
<from xsi:type="xsd:string">27999000224</from>
<timestamp xsi:type="xsd:int">1213690834</timestamp>
<status xsi:type="xsd:int">003</status>
<charge xsi:type="xsd:float">0.300000</charge>
</tns:mt_callback>
</SOAP-ENV:Body>
</SOAP-ENV:Envelope>
```

This is an example callback URL that will be sent to your application:

```
http://www.yoursite.com/your_url.php?data="<?xml version="1.0" encoding="ISO-8859-1"?><SOAP-
ENV:Envelope SOAP-ENV:encodingStyle="http://schemas.xmlsoap.org/soap/encoding/" xmlns:SOAP-
ENV="http://schemas.xmlsoap.org/soap/envelope/" xmlns:xsd="http://www.w3.org/2001/XMLSchema"
xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance" xmlns:SOAP-
ENC="http://schemas.xmlsoap.org/soap/encoding/" xmlns:tns="mt_callback"><SOAP-ENV:Body>
<tns:mt_callback xmlns:tns="mt_callback"><api_id xsi:type="xsd:int">1234</api_id>
<apimsgid xsi:type="xsd:string">2e838df2ee3ea418272ae05aaf84ce5d</apimsgid><climsgid
xsi:type="xsd:string">abc123</climsgid><to xsi:type="xsd:string">27999123456</to>
<from xsi:type="xsd:string">27999000224</from><timestamp
xsi:type="xsd:int">1213690834</timestamp><status xsi:type="xsd:int">003</status>
<charge xsi:type="xsd:float">0.300000</charge></tns:mt_callback></SOAP-ENV:Body></SOAP-
ENV:Envelope>"
```

8.2.5 Delivery time <deliv_time>

The delivery of an SMS message may be delayed by setting an amount of time in **minutes** relative to the time at which it was received by our gateway. We will store the message until the required time frame has elapsed. The maximum delay time is 10080 minutes or 7 days.

When sending batches of messages, the delivery time should be set in the *startbatch* command. This will ensure that all messages are delivered X minutes after being posted to the Gateway.

8.2.6 Concatenation <concat>

If this value is set to 1, 2 or 3 the message will span across 1, 2 or 3 SMS messages where applicable. One text SMS will be sent for every 160 characters or 140 bytes. If a message is concatenated, it reduces the number of characters contained in each message by 7. With 8-bit concatenated messages, each SMS can support up to 140 bytes including the UDH headers.

Please also see http://support.clickatell.com/faq.php?mode=view_entry&kbid=121&kbcats=26 for information on characters that require two character places.

Please be aware that a single Unicode SMS can only contain a maximum of 70 characters. If a Unicode message is concatenated, it reduces the number of characters contained in each message part by 7.

Values set are:

Value	Status
1	Default - No concatenation: only 1 message.
2	Concatenate a maximum of 2 messages.
3	Concatenate a maximum of 3 messages.
N	Concatenate a maximum of N messages. (Delivery is dependent on mobile and gateway. A maximum of 3 is recommended).

8.2.7 Maximum credits <max_credits>

This parameter overrides the maximum charge associated with message delivery, as set by the profiles selected within your client account after logging in online. This parameter can be used to limit the cost of a message to a particular value and is bound by the maximum credit value specified in your profiles.

A valid API message ID can still be returned for messages that are not delivered as a result of the maximum credits value set. These messages will have a status of routing error (009).

The credit value in this parameter can be set to any amount of credits. To set your delivery profile, go to **Central>>My Settings>>Routing Profiles**.

8.2.8 Required features <req_feat>

This parameter specifies the features that must be present in order for message delivery to occur. If all features are not present, the message will not be delivered. This prevents SMS messages arriving at a destination via the least-cost gateway, without certain features. This would, for instance, prevent the dropping of a sender ID.

This means that we will not route messages through a gateway that cannot support the required features you have set. For certain message types, we always set the required feature bitmask where relevant. These are FEAT_8BIT, FEAT_UDH, FEAT_UCS2 and FEAT_CONCAT.

This parameter is set using a combined decimal number to refer to the additional required features.

E.g.: $32 + 512 = 544$ – Numeric sender ID and Flash SMS both required.

The value you would set to ensure that Flash and numeric sender ID are both supported, would therefore be **544**.

To ensure that delivery acknowledgment and alphanumeric IDs are supported you would use the value **8240** ($16 + 32 + 8192$).

Hex value	Decimal	Feature	Description
0x0001	1	FEAT_TEXT	Text – set by default.
0x0002	2	FEAT_8BIT	8-bit messaging – set by default.
0x0004	4	FEAT_UDH	UDH (Binary) - set by default.
0x0008	8	FEAT_UCS2	UCS2 / Unicode – set by default.
0x0010	16	FEAT_ALPHA	Alpha source address (from parameter).

Hex value	Decimal	Feature	Description
0x0020	32	FEAT_NUMER	Numeric source address (from parameter).
0x0200	512	FEAT_FLASH	Flash messaging.
0x2000	8192	FEAT_DELIVACK	Delivery acknowledgments.
0x4000	16384	FEAT_CONCAT	Concatenation – set by default.

8.2.9 Delivery queue <queue>

Setting this parameter will assign the message to one of three queues assigned to each user account. This sets the priority of a message sent to us, relative to other messages sent from the same user account. Messages in queue number 1, will always be delivered before messages in queue number 2 and 3, while messages in the 3rd queue, will have the lowest priority (relative to queues 1 and 2).

This is useful when delivering, for example, a single high priority message while you have a large batch going through that same account. The large batch will be queued through queue number 3 (default), and urgent alerts (sent through queue 1), will be delivered ahead of those messages in the batch (queue 3), regardless of when they are actually sent to us.

Values set are:

Value	Status
1	Use first / primary user queue (highest priority).
2	Use second user queue.
3	Use third user queue (lowest priority) - Default status.

8.2.10 Gateway escalation <escalate>

By default, the message router will select the lowest cost route (matching features and reliability) that is available for a given destination.

This parameter ensures that, should a message be delayed due to gateway congestion or some other reason on the initial gateway selected by our router, then alternative routes that match the required features will be sought. This is done by moving through the available gateways in order of increasing cost, up to the maximum charge set by the user either using the parameter that defines the maximum credits or based on the profiles selected.

When urgent and high priority messages are sent, they should be posted with escalate set to 1 (on), combined with a high maximum credit value to ensure that the greatest number of gateways are available.

Values set are:

Value	Status
0	Off – Default value.
1	On - If the least-cost route has messages queued then escalate

immediately to an alternative route.

8.2.11 Mobile originated <mo>

This parameter is only used when a message is sent to a handset and a reply is expected.

PLEASE NOTE: This parameter is only valid for clients that have signed up and paid for our two-way messaging service. An alternative to our least-cost gateway may be used, which could result in a higher cost per message. Please email Clickatell [support](#) for pricing or view online.

When sending a normal MT message to a handset and you expect a reply to your registered MO number, please set the **mo** parameter to "1".

Values to set are:

Value	Status
0	Off - Default status. We use the normal routing feature.
1	Enables reply ability. We route via a pre-defined carrier to enable the ability to reply.

It is important that the user specifies the correct **from** parameter together with this parameter. If no **from** parameter is specified, we will use a default originator number as set by Clickatell. You will NOT receive these replies.

If you specify the originator (the purchased mo number), then we will route the message such that it can be replied to by the recipient. This reply will be sent to you.

8.2.12 Client message ID <cliMsgid>

This parameter is set by the user to enable internal message tracking. It allows the user to set their own tracking ID for each message. Once set for a given message, this may be used in place of the Clickatell issued API message ID (apimsgid) for querying message.

A client message ID (climsgid) may be any combination of alphanumeric characters excluding spaces. A maximum of 32 characters may be used.

Client message IDs may be used with the *querymsg* command.

8.2.13 Unicode <unicode>

If this value is set to 1, the text field must contain two-byte UTF-16 Unicode. Each SMS can handle a maximum of 70 characters. Each Unicode character must be hex-encoded. More information is available at <http://www.Unicode.org/>.

Note: When using the batch send facility for delivering Unicode messages, it is not possible to substitute variables into the message content. This is only possible with Germanic characters.

Values set are:

Value	Status
0	Off - default status.
1	On - delivers the text as two-byte Unicode.

We provide a converter to convert text to Unicode within your client account online. Go to “Converters” from within your account online.

8.2.14 Message type <msg_type>

A wide variety of messages can be sent through our gateway. We have pre-defined a number of SMS message-types in the API, so that you do not have to set the UDH (user data header) manually. You may optionally set the UDH rather than using one of the message types set below. Message types are case sensitive.

For non-Nokia message types (EMS, etc.), please generate your own UDH and data according to the manufacturers specifications of the message type you wish to send.

This parameter need not be included if the SMS is a standard text message.

Values set are:

Value	Description
SMS_TEXT	This is the default message type. It is optional to specify this parameter.
SMS_FLASH	To send an SMS that displays immediately upon arrival at the phone.
SMS_NOKIA_OLOGO	Send an operator logo to a Nokia handset.
SMS_NOKIA_GLOGO	Send a group logo to a Nokia handset.
SMS_NOKIA_PICTURE	Send a picture message to certain Nokia handsets.
SMS_NOKIA_RINGTONE	Send a ringtone to a Nokia handset.
SMS_NOKIA_RTTL	Send an RTTTL format ringtone to Nokia handsets.
SMS_NOKIA_CLEAN	Remove operator logo from a Nokia handset.
SMS_NOKIA_VCARD	Send a business card to a Nokia handset.
SMS_NOKIA_VCAL	Send an event calendar to a Nokia handset.

8.2.15 Validity period <validity>

A message may be given a time frame for which it is valid. After this period the message will expire. This parameter takes an amount of time in **minutes** relative to the time at which the message was received by our gateway. If the message is queued on our gateway for a period exceeding the validity period set then a routing error of 115 will be returned. The default validity period is 1440 minutes (24 hours).

Note: The validity period is not passed on to the upstream gateway.

9. Additional Commands

Please note that where commands require a **sessionid** for authentication or **apid_id**, **username** and **password** can be used instead.

9.1 Delete/Stop message

This enables you to stop the delivery of a particular message. This command can only stop messages which may be queued within our router, and not messages which have already been delivered to a SMSC. This command is therefore only really useful for messages with deferred delivery times.

Name:	delMsg				
Parameters:	<table border="0"> <tr> <td>session_id</td> <td>Required</td> </tr> <tr> <td>apiMsgId or cliMsgId</td> <td>Required</td> </tr> </table>	session_id	Required	apiMsgId or cliMsgId	Required
session_id	Required				
apiMsgId or cliMsgId	Required				

Name:	delMsg Response			
Response Values:	<table border="0"> <tr> <td>ID: xxxx Status: xxxx</td> </tr> <tr> <td>or</td> </tr> <tr> <td>ERR: Error number</td> </tr> </table>	ID: xxxx Status: xxxx	or	ERR: Error number
ID: xxxx Status: xxxx				
or				
ERR: Error number				

9.2 Query balance

This will return the number of credits available on this particular account. The account balance is returned as a floating point value.

Name:	getBalance		
Desc:	This enables you to determine your account balance.		
Parameters:	<table border="0"> <tr> <td>session_id</td> <td>Required</td> </tr> </table>	session_id	Required
session_id	Required		

Name:	getBalance Response			
Response Values:	<table border="0"> <tr> <td>Credit: xxxx.x</td> </tr> <tr> <td>or</td> </tr> <tr> <td>ERR: Error number</td> </tr> </table>	Credit: xxxx.x	or	ERR: Error number
Credit: xxxx.x				
or				
ERR: Error number				

9.3 Coverage query

This command enables users to check our coverage of a network or number, without sending a message to that number. Authentication is required for this API call. This call should NOT be used before sending each message.

A response tag of ok indicates it is covered, while a fault tag indicates that the destination is not covered. Contact support to enquire about obtaining coverage for this destination.

Name:	routeCoverage	
Parameters:	msisdn	Required
	session_id	Required

Name:	routeCoverage Response
Response Values:	OK: This prefix is currently supported. Messages sent to this prefix will be routed. Charge: 1 or ERR: This prefix is not currently supported. Messages sent to this prefix will fail. Please contact support for assistance.

9.4 MMS Push

When an MMS message is sent to a phone, the mobile device receives an MMS notification message via SMS. When this MMS notification message is received by the mobile device, the mobile device automatically initiates a WAP gateway connection to download the content of the MMS message, from a URL specified in the SMS notification message. This command enables users to send an MMS notification message. Authentication is required for this API call.

MMS documentation (WAP-209-MMSEncapsulation-20020105-a.pdf, Version 05-Jan-2002) can be found at <http://www.openmobilealliance.org/tech/affiliates/wap/wapindex.html>.

Parameter	Description	Example	Default value	Restricted value	Required
mms_subject	Subject	My+message			yes
mms_class	Class	80		80 (Personal) 81 (Advertisement) 82 (Informational) 83 (Auto)	yes
mms_expire	How long before the MMS expires	3000		Time in seconds	yes
mms_from	From text	John			yes
mms_url	URL with the MMS content. The URL must be	http://www.mywebsite.com/example.mms			yes

	URL encoded.				
--	--------------	--	--	--	--

Name:	ind_push	
Parameters:	session_id	Required
	mms_subject	Required
	mms_class	[Optional]
	mms_expire	[Optional]
	mms_from	[Optional]
	mms_url	[Optional]

Name:	ind_push Response	
Response Values:	ID: xxxx To: xxxx	
	or	
	ERR: Error number	

9.5 WAP push service indication

WAP Push Service Indication (SI) is a WAP address embedded within the header of a specially formatted SMS. This is displayed as an alert message to the user, and gives the user the option of connecting directly to a particular URL via the handsets WAP browser (if supported). This command enables you to send a WAP Push Service Indication.

Please note: Incorrect date formats for si_created and si_expires may lead to handsets discarding messages with delivery receipts.

WAP documentation (WAP-167-ServiceInd-20010731-a.pdf, Version 31-July-2001) can be found at <http://www.openmobilealliance.org/tech/affiliates/wap/wapindex.html>.

Parameter	Description	Example	Default value	Restricted values	Required
si_id	Unique ID for each message				Yes
si_url	The URL that is used to access the service or content. The URL must be URL encoded.	http://www.65mydomain.com?picture=6566			Yes
si_text	Notification text. Provides a means to specify additional information.	Here is your picture.			Yes
si_created	A date in UTC (Coordinated Universal Time) format. Used to specify the date and	2008-01-01T19:30:41Z			No

Parameter	Description	Example	Default value	Restricted values	Required
	time associated with the creation or last modification of the content indicated by the URL, which may differ from the date and time when the SI was created.				
si_expires	Expiry date in UTC format. This allows you to specify a time after which the SI will automatically be deleted from the handset. If not specified it will never expire.	2008-12-12T19:30:40Z			No
si_action	A string specifying the action to be taken when the SI is received.		signal-medium,	signal-none, signal-low, signal-medium, signal-high, delete.	No

Name:	si_push	
Parameters:	session_id si_id si_url si_text si_created si_expires si_action	Required Required [Optional] [Optional] [Optional] [Optional] [Optional]

Name:	si_push Response
Response Values:	ID: xxxx To: xxxx or ERR: Error number

9.6 Get message charge query

This command enables the user to query both the status and charge of a delivered message in a single API call. Authentication is required for this API call and will only work for messages less than 15 days old. Clickatell can also post the message charge to your application via means of a *Callback URL* (this is

the preferred method). Detailed information can be found in the “Callback URL” section under “Message parameters”.

Name:	getMsgCharge	
Parameters:	session_id apiMsgId	Required Required

Name:	getMsgCharge Resp	
Response Values:	apiMsgId: xxxx charge: xxx status: xxx or ERR: Error number	

9.7 Token (voucher) pay

This command allows you to spend a voucher that has been generated, within your client account, after logging in online. This is very useful for topping up sub-users accounts with credits. You would generate a session ID for the sub-user account, into which you wish to add the credits. You may also use the standard login details. The voucher number is currently a 16 digit numeric value.

Name:	tokenPay	
Parameters:	session_id token	Required Required

Name:	tokenPay Response	
Response Values:	OK: 605 - If the payment was successful or ERR: 606, Invalid Voucher ERR: 607, Expired Voucher	

10. Batch messaging

This facility enables one to do high volume delivery and server-side message merging. It offers the end-user the ability to define all elements common to a batch, and then send only the parameters that change on a message by message basis.

One initially defines a batch using the *startbatch* command, which will return a unique batch ID. You then use either *senditem* or *quicksend* with the batch ID, depending on whether the message needs to be personalised. See SMS examples below.

Hi #field1#, your doctor's appointment is at #field2# tomorrow, could become:
 Hi Fred, your doctor's appointment is at 10:30 tomorrow.
 Hi Jane, your doctor's appointment is at 14:00 tomorrow.

10.1 Start batch

Once you have issued this command, you will be returned a batch ID that is to be used when sending multiple batch items. Included functionality also allows for message merging where you can substitute fields that you have defined in your template. The field names are called *field1* though to *fieldN*.

This command can take all the parameters of *sendmsg*, with the addition of a template, and the exception of both the destination address and the text fields. It must be used before either the *senditem* or *quicksend* command.

Name:	startBatch	
Parameters:	session_id	Required
	template	Required
	callback	[Optional]
	cliMsgId	[Optional]
	concat	[Optional]
	deliv_ack	[Optional]
	deliv_time	[Optional]
	escalate	[Optional]
	from	[Optional]
	max_credits	[Optional]
	msg_type	[Optional]
	queue	[Optional]
	req_feat	[Optional]
	udh	[Optional]
	unicode	[Optional]
	validity	[Optional]

Name:	startBatch Response	
Response Values:	ID: batch id	
	or	
	ERR: Error number	

10.2 Sending messages to existing batch

Send a message to a batch passing the destination mobile number and optional field replacement values. The fields 1-4 that you defined in the *startbatch* command are used to optionally personalise the message.

Name:	sendItem	
Parameters:	session_id batch_id to fields	Required Required Required [Optional]

Set the field values as per the template set up in *startbatch* command tag. This tag can only be used within *sendItem* command tag

Name:	fields	
Parameters:	field1 field2 field3 field4	Required [Optional] [Optional] [Optional]

Name:	sendItem Response	
Response Values:	ID: apimsgid or ERR: Error number	

10.3 Quick send to batch

Where one has the requirement to send the same message to multiple recipients, you can use the *quickSend* command. This command offers low overhead and maximum throughput. It is essentially a reference to a predefined template and a string of destination addresses.

Name:	quickSend	
Parameters:	session_id batch_id to	Required Required Required

Name:	quickSend Response	
Response Values:	ID: apimsgid To: xxxxx or ERR: Error number To: xxxxxx	

10.4 End batch

This command ends a batch and is not required (following a batch send). Batches will expire automatically after 24 hours.

Name:	endBatch
-------	----------

Parameters:	session_id batch_id	Required Required
-------------	------------------------	----------------------

Name:	endBatch Response
Response Values:	OK or ERR: Error number

11. Message examples

Here are some example URLs that demonstrate how to use the API. All values in these examples should be replaced by your own values.

11.1 Simple examples

sendmsg operation including authentication and sender ID:

```
<?xml version="1.0" encoding="ISO-8859-1"?>
<SOAP-ENV:Envelope SOAP-ENV:encodingStyle="http://schemas.xmlsoap.org/soap/encoding/"
xmlns:SOAP-ENV="http://schemas.xmlsoap.org/soap/envelope/"
xmlns:xsd="http://www.w3.org/2001/XMLSchema"
xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance" xmlns:SOAP-
ENC="http://schemas.xmlsoap.org/soap/encoding/" xmlns:tns="soap.clickatell.com">
  <SOAP-ENV:Body>
    <tns:sendmsg xmlns:tns="soap.clickatell.com">
      <session_id xsi:nil="true" xsi:type="xsd:string"/>
      <api_id xsi:type="xsd:int">1234</api_id>
      <user xsi:type="xsd:string">demo</user>
      <password xsi:type="xsd:string">demo</password>
      <to xsi:type="SOAP-ENC:Array" SOAP-ENC:arrayType="xsd:string[2]">
        <item xsi:type="xsd:string">2799912345</item>
        <item xsi:type="xsd:string">27999123134</item>
      </to>
      <from xsi:type="xsd:string">me</from>
      <text xsi:type="xsd:string">Initial test message</text>
      <concat xsi:nil="true" xsi:type="xsd:int"/>
      <deliv_ack xsi:nil="true" xsi:type="xsd:int"/>
      <callback xsi:nil="true" xsi:type="xsd:int"/>
      <deliv_time xsi:nil="true" xsi:type="xsd:int"/>
      <max_credits xsi:nil="true" xsi:type="xsd:float"/>
      <req_feat xsi:nil="true" xsi:type="xsd:int"/>
      <queue xsi:nil="true" xsi:type="xsd:int"/>
      <escalate xsi:nil="true" xsi:type="xsd:int"/>
      <mo xsi:nil="true" xsi:type="xsd:int"/>
      <cliMsgId xsi:nil="true" xsi:type="xsd:string"/>
      <unicode xsi:nil="true" xsi:type="xsd:int"/>
      <msg_type xsi:nil="true" xsi:type="xsd:string"/>
      <udh xsi:nil="true" xsi:type="xsd:string"/>
      <data xsi:nil="true" xsi:type="xsd:string"/>
    </tns:sendmsg>
  </SOAP-ENV:Body>
</SOAP-ENV:Envelope>
```

```

    <validity xsi:nil="true" xsi:type="xsd:int" />
  </tns:sendmsg>
</SOAP-ENV:Body>
</SOAP-ENV:Envelope>

```

Initial authentication:

```

<?xml version="1.0" encoding="ISO-8859-1"?>
  <SOAP-ENV:Envelope SOAP-
ENV:encodingStyle="http://schemas.xmlsoap.org/soap/encoding/" xmlns:SOAP-
ENV="http://schemas.xmlsoap.org/soap/envelope/"
xmlns:xsd="http://www.w3.org/2001/XMLSchema"
xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance" xmlns:SOAP-
ENC="http://schemas.xmlsoap.org/soap/encoding/" xmlns:tns="soap.clickatell.com">
  <SOAP-ENV:Body>
    <tns:auth xmlns:tns="soap.clickatell.com">
      <api_id xsi:type="xsd:int">1234</api_id>
      <user xsi:type="xsd:string">demo</user>
      <password xsi:type="xsd:string">demo</password>
    </tns:auth>
  </SOAP-ENV:Body>
</SOAP-ENV:Envelope>

```

Account balance:

```

<?xml version="1.0" encoding="ISO-8859-1"?>
<SOAP-ENV:Envelope SOAP-ENV:encodingStyle="http://schemas.xmlsoap.org/soap/encoding/"
xmlns:SOAP-ENV="http://schemas.xmlsoap.org/soap/envelope/"
xmlns:xsd="http://www.w3.org/2001/XMLSchema"
xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance" xmlns:SOAP-
ENC="http://schemas.xmlsoap.org/soap/encoding/" xmlns:tns="soap.clickatell.com">
  <SOAP-ENV:Body>
    <tns:getbalance xmlns:tns="soap.clickatell.com">
      <session_id xsi:nil="true" xsi:type="xsd:string" />
      <api_id xsi:type="xsd:int">1234</api_id>
      <user xsi:type="xsd:string">demo</user>
      <password xsi:type="xsd:string">demo</password>
    </tns:getbalance>
  </SOAP-ENV:Body>
</SOAP-ENV:Envelope>

```

Query message status:

```

<?xml version="1.0" encoding="ISO-8859-1"?>
<SOAP-ENV:Envelope SOAP-ENV:encodingStyle="http://schemas.xmlsoap.org/soap/encoding/"
xmlns:SOAP-ENV="http://schemas.xmlsoap.org/soap/envelope/"
xmlns:xsd="http://www.w3.org/2001/XMLSchema"
xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance" xmlns:SOAP-
ENC="http://schemas.xmlsoap.org/soap/encoding/" xmlns:tns="soap.clickatell.com">
  <SOAP-ENV:Body>
    <tns:querymsg xmlns:tns="soap.clickatell.com">
      <session_id
xsi:type="xsd:string">330df12c75bf8046942c3304639aa646</session_id>
      <api_id xsi:nil="true" xsi:type="xsd:int" />
      <user xsi:nil="true" xsi:type="xsd:string" />
      <password xsi:nil="true" xsi:type="xsd:string" />
    </tns:querymsg>
  </SOAP-ENV:Body>
</SOAP-ENV:Envelope>

```

```

    <apimsgid
xsi:type="xsd:string">37e06b93444d607285226387390e299c</apimsgid>
    <climsgid xsi:nil="true" xsi:type="xsd:string"/>
  </tns:querymsg>
</SOAP-ENV:Body>
</SOAP-ENV:Envelope>

```

11.2 Batch SMS examples

11.2.1 Sending a personalised message to multiple recipients

To start the batch:

```

<?xml version="1.0" encoding="ISO-8859-1"?>
<SOAP-ENV:Envelope SOAP-ENV:encodingStyle="http://schemas.xmlsoap.org/soap/encoding/"
xmlns:SOAP-ENV="http://schemas.xmlsoap.org/soap/envelope/"
xmlns:xsd="http://www.w3.org/2001/XMLSchema"
xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance" xmlns:SOAP-
ENC="http://schemas.xmlsoap.org/soap/encoding/" xmlns:tns="soap.clickatell.com">
  <SOAP-ENV:Body>
    <tns:startbatch xmlns:tns="soap.clickatell.com">
      <session_id
xsi:type="xsd:string">330df12c75bf8046942c3304639aa646</session_id>
      <api_id xsi:nil="true" xsi:type="xsd:int"/>
      <user xsi:nil="true" xsi:type="xsd:string"/>
      <password xsi:nil="true" xsi:type="xsd:string"/>
      <from xsi:nil="true" xsi:type="xsd:string"/>
      <concat xsi:nil="true" xsi:type="xsd:int"/>
      <template xsi:type="xsd:string">Hi #field1# this is a personalised
message</template>
      <deliv_ack xsi:nil="true" xsi:type="xsd:int"/>
      <callback xsi:nil="true" xsi:type="xsd:int"/>
      <deliv_time xsi:nil="true" xsi:type="xsd:int"/>
      <max_credits xsi:nil="true" xsi:type="xsd:float"/>
      <req_feat xsi:nil="true" xsi:type="xsd:int"/>
      <queue xsi:nil="true" xsi:type="xsd:int"/>
      <escalate xsi:nil="true" xsi:type="xsd:int"/>
      <mo xsi:nil="true" xsi:type="xsd:int"/>
      <cliMsgId xsi:nil="true" xsi:type="xsd:string"/>
      <unicode xsi:nil="true" xsi:type="xsd:int"/>
      <msg_type xsi:nil="true" xsi:type="xsd:string"/>
      <udh xsi:nil="true" xsi:type="xsd:string"/>
      <data xsi:nil="true" xsi:type="xsd:string"/>
      <validity xsi:nil="true" xsi:type="xsd:int"/>
    </tns:startbatch>
  </SOAP-ENV:Body>
</SOAP-ENV:Envelope>

```

To end the batch:

```

<?xml version="1.0" encoding="ISO-8859-1"?>
<SOAP-ENV:Envelope SOAP-ENV:encodingStyle="http://schemas.xmlsoap.org/soap/encoding/"
xmlns:SOAP-ENV="http://schemas.xmlsoap.org/soap/envelope/"
xmlns:xsd="http://www.w3.org/2001/XMLSchema"
xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance" xmlns:SOAP-
ENC="http://schemas.xmlsoap.org/soap/encoding/" xmlns:tns="soap.clickatell.com">

```

```

    <SOAP-ENV:Body>
      <tns:endbatch xmlns:tns="soap.clickatell.com">
        <session_id
xsi:type="xsd:string">330df12c75bf8046942c3304639aa646</session_id>
        <api_id xsi:nil="true" xsi:type="xsd:int"/>
        <user xsi:nil="true" xsi:type="xsd:string"/>
        <password xsi:nil="true" xsi:type="xsd:string"/>
        <batch_id
xsi:type="xsd:string">630d9a8b093b4f0c13392ff0e0e4f863</batch_id>
      </tns:endbatch>
    </SOAP-ENV:Body>
  </SOAP-ENV:Envelope>

```

11.2.2 Sending a personalised message

```

<?xml version="1.0" encoding="ISO-8859-1"?>
<SOAP-ENV:Envelope SOAP-ENV:encodingStyle="http://schemas.xmlsoap.org/soap/encoding/"
xmlns:SOAP-ENV="http://schemas.xmlsoap.org/soap/envelope/"
xmlns:xsd="http://www.w3.org/2001/XMLSchema"
xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance" xmlns:SOAP-
ENC="http://schemas.xmlsoap.org/soap/encoding/" xmlns:tns="soap.clickatell.com">
  <SOAP-ENV:Body>
    <tns:senditem xmlns:tns="soap.clickatell.com">
      <session_id
xsi:type="xsd:string">330df12c75bf8046942c3304639aa646</session_id>
      <api_id xsi:nil="true" xsi:type="xsd:int"/>
      <user xsi:nil="true" xsi:type="xsd:string"/>
      <password xsi:nil="true" xsi:type="xsd:string"/>
      <batch_id
xsi:type="xsd:string">a96d70df18b7b56f2965e816c76d317b</batch_id>
      <to xsi:type="SOAP-ENC:Array" SOAP-ENC:arrayType="xsd:string[1]">
        <item xsi:type="xsd:string">27999123454</item>
      </to>
      <field1 xsi:type="xsd:string">John</field1>
      <field2 xsi:nil="true" xsi:type="xsd:string"/>
      <field3 xsi:nil="true" xsi:type="xsd:string"/>
      <field4 xsi:nil="true" xsi:type="xsd:string"/>
    </tns:senditem>
  </SOAP-ENV:Body>
</SOAP-ENV:Envelope>

```

11.2.3 Sending multiple SMS using batches

```

<?xml version="1.0" encoding="ISO-8859-1"?>
<SOAP-ENV:Envelope SOAP-ENV:encodingStyle="http://schemas.xmlsoap.org/soap/encoding/"
xmlns:SOAP-ENV="http://schemas.xmlsoap.org/soap/envelope/"
xmlns:xsd="http://www.w3.org/2001/XMLSchema"
xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance" xmlns:SOAP-
ENC="http://schemas.xmlsoap.org/soap/encoding/" xmlns:tns="soap.clickatell.com">
  <SOAP-ENV:Body>
    <tns:quicksend xmlns:tns="soap.clickatell.com">
      <session_id
xsi:type="xsd:string">330df12c75bf8046942c3304639aa646</session_id>
      <api_id xsi:nil="true" xsi:type="xsd:int"/>
      <user xsi:nil="true" xsi:type="xsd:string"/>
      <password xsi:nil="true" xsi:type="xsd:string"/>
    </tns:quicksend>
  </SOAP-ENV:Body>
</SOAP-ENV:Envelope>

```

```
        <batch_id  
xsi:type="xsd:string">a96d70df18b7b56f2965e816c76d317b</batch_id>  
        <to xsi:type="SOAP-ENC:Array" SOAP-ENC:arrayType="xsd:string[3]">  
            <item xsi:type="xsd:string">2799912345</item>  
            <item xsi:type="xsd:string">27999123134</item>  
            <item xsi:type="xsd:string">2799923424</item>  
        </to>  
    </tns:quicksend>  
</SOAP-ENV:Body>  
</SOAP-ENV:Envelope>
```

12. Appendix A: Error codes

The following list of error messages are generated by the Clickatell gateway during a validation phase before we accept the message. These error messages are sent back to your application. There will be no message charge if these errors are generated when sending a message. Data regarding messages that do not pass initial validation will not be included in your Clickatell Central reports.

Number	Description	Detail
001	Authentication failed	
002	Unknown username or password	
003	Session ID expired	
004	Account frozen	
005	Missing session ID	
007	IP Lockdown violation	You have locked down the API instance to a specific IP address and then sent from an IP address different to the one you set.
101	Invalid or missing parameters	
102	Invalid user data header	
103	Unknown API message ID	
104	Unknown client message ID	
105	Invalid destination address	
106	Invalid source address	
107	Empty message	
108	Invalid or missing API ID	
109	Missing message ID	This can be either a client message ID or API message ID. For example when using the stop message command.
110	Error with email message	
111	Invalid protocol	
112	Invalid message type	
113	Maximum message parts exceeded	The text message component of the message is greater than the permitted 160 characters (70 Unicode characters). Select concat equal to 1,2,3-N to overcome this by splitting the message across multiple messages.
114	Cannot route message	This implies that the gateway is not currently routing messages to this network prefix. Please email support@clickatell.com with

		the mobile number in question.
115	Message expired	
116	Invalid Unicode data	
120	Invalid delivery time	
121	Destination mobile number blocked	This number is not allowed to receive messages from us and has been put on our block list.
122	Destination mobile opted out	
123	Invalid Sender ID	A sender ID needs to be registered and approved before it can be successfully used in message sending.
128	Number delisted	This error may be returned when a number has been delisted.
201	Invalid batch ID	
202	No batch template	
301	No credit left	
302	Max allowed credit	

13. Appendix B: Message statuses

These are message statuses that are generated after the Clickatell gateway has accepted the message for delivery. Data regarding messages passing initial validation and accepted for delivery will be included in your Clickatell Central reports.

Number	Hex	Description	Detail
001	0x001	Message unknown	The message ID is incorrect or reporting is delayed.
002	0x002	Message queued	The message could not be delivered and has been queued for attempted redelivery.
003	0x003	Delivered to gateway	Delivered to the upstream gateway or network (delivered to the recipient).
004	0x004	Received by recipient	Confirmation of receipt on the handset of the recipient.
005	0x005	Error with message	There was an error with the message, probably caused by the content of the message itself.
006	0x006	User cancelled message delivery	The message was terminated by a user (stop message command) or by our staff.

007	0x007	Error delivering message	An error occurred delivering the message to the handset.
008	0x008	OK	Message received by gateway.
009	0x009	Routing error	The routing gateway or network has had an error routing the message.
010	0x00A	Message expired	Message has expired before we were able to deliver it to the upstream gateway. No charge applies.
011	0x00B	Message queued for later delivery	Message has been queued at the gateway for delivery at a later time (delayed delivery).
012	0x00C	Out of credit	The message cannot be delivered due to a lack of funds in your account. Please re-purchase credits.

14. Terminology

- **Mobile originated (MO):** A message sent (originating) from a mobile handset to an application via Clickatell.
- **Mobile terminated (MT):** A message sent from an application to (terminating on) a mobile handset via Clickatell.
- **Premium rated message (MO):** A mobile user is charged a premium for the message that they send to a particular short or long code. This service is not available in all regions; please contact an Account Manager for more information.
- **Premium rated message (MT):** A mobile user is charged a premium for a message that they receive from a particular short or long code. This service is not available in all regions; please contact an Account Manager for more information.
- **Revenue share:** This refers to the portion of the premium charge associated with a premium rated message, which is passed on to the content provider.
- **Content provider:** This is the Clickatell customer who is offering one or more services that are usually premium rated SMS system.
- **Customer:** A registered Clickatell customer utilising the Clickatell API for message delivery and receipt.
- **Sender ID:** The "from" address that appears on the user's handset. This is also known as the message originator or source address. A Sender ID must be registered within your account and approved by us before it may be used.
- **Destination address:** The mobile number/MSISDN of the handset to which the message must be delivered. The number should be in international number format, e.g. country code + local mobile number, excluding the leading zero (0).
- **Source address:** See 'Sender ID' above.
- **Short code:** A short number which is common across all the operators for a specific region.
- **Subscriber:** The mobile network subscriber who owns the mobile number (MSISDN) which will send or receive SMSs, or be billed for premium rated services.
- **Upstream gateway:** A network operator, third party or our own short message service centre (SMSC).

15. Contact details

Phone: +27 21 910 7700
Fax: +27 21 910 7701
Website: www.clickatell.com
Help URL: <http://support.clickatell.com/index.php>
Support: support@clickatell.com
Info: info@clickatell.com
Sales: sales@clickatell.com

--- 0 ---